



## Question / Issue

**(solid works)** The error message “Error opening c:\program files\mastercam x3 mu1 for solidworks\config\mcamx.config” appears when trying to load MCfSW.


## Answer / Solution

The below error message appears when attempting to load Mastercam for SolidWorks on a Vista system:



**Cause:** Vista User Account Control (UAC) blocks Mastercam from creating the Mcamx.config on startup.


**Solution:** Disable User Account Control, “UAC” in Windows Control Panel under User Accounts.



**(Bad RC)** User is getting a “Bad RC from DllRegisterServer” error message when trying to register files with the Mastercam Applet or regsvr32.

## Answer / Solution

The user is getting the below error message when trying to register a file using the Mastercam Control Panel Applet or regsvr32.exe in Windows Vista:



**Cause:** Vista User Account Control is blocking the file from being registered.

*Note: The “UAC” also appears to be blocking the registration of files during the install as well. So when a user tries to open a SolidWorks file, for example, they will get the “Cannot find Parasolid data in SolidWorks file” error. They try to manually register that file and get then get the error above.*

**Solution:** Disable User Account Control, “UAC” in Windows Control Panel under User Accounts.

